

Certificate of Analysis

Powered by Confident Cannabis

Cannabis Care

XXXX Vancouver Island, BC XXX XXX help@cannabiscare.cc (888) 798-6710 Lic. #

Sample: 2108PURA0440.1409

Strain: Medi Hash Batch#: ; Batch Size: 1 g

Sample Received: 08/16/2021; Report Created: 08/18/2021

Medi Hash

Concentrates & Extracts, Hash - Hard





17.736% 21.136%

Total THC Cannabinoids

0.259% NT

Total CBD Moisture

Not Tested

Foreign Matter

Cannabinoids

Analyte	LOQ	Mass	Mass	
	%	%	mg/g	
THCa	0.010	4.715	47.15	
Δ9-ΤΗС	0.010	13.601	136.01	
Δ8-THC	0.010	ND	ND	
THCVa	0.010	0.048	0.48	
THCV	0.010	0.245	2.45	
CBDa	0.010	0.228	2.28	
CBD	0.010	0.059	0.59	
CBDVa	0.010	ND	ND	
CBDV	0.010	ND	ND	
CBN	0.010	0.681	6.81	
CBGa	0.010	0.399	3.99	
CBG	0.010	0.378	3.78	
CBCa	0.010	0.120	1.20	
CBC	0.010	0.662	6.62	
Δ10-THC	0.010	ND	ND	
Total		21.136	211.36	

PURA ANALYTICAL LABS

Method: HPLC-DAD. LOQ = Limit of Quantitation; ND = Not Detectable, NR = Not Reported, NT = Not Tested. Unless otherwise stated all quality control samples performed within specifications established by the Laboratory. When reporting totals, acidic cannabinoids are multiplied by 0.877 to account for loss of mass from decarboxylation upon heating; therefore this is the POTENTIAL amount upon complete decarboxylation from smoking/vaping.



PURA ANALYTICAL LABS

1140 Fisher Road Cobble Hill, BC (250) 929-2002 https://www.puralabs.ca Lic# LIC-RJMAT2OG6I-2019

Jeh

Denise Johnson Head of Laboratory Confident Cannabis All Rights Reserved support@confidentcannabis.com (866) 506-5866 www.confidentcannabis.com





Certificate of Analysis

Powered by Confident Cannabis 2 of 3

Cannabis Care

XXXX Vancouver Island, BC XXX XXX help@cannabiscare.cc (888) 798-6710 Lic. #

Sample: 2108PURA0440.1409

Strain: Medi Hash Batch#: ; Batch Size: 1 g

Sample Received: 08/16/2021; Report Created: 08/18/2021

Medi Hash

Concentrates & Extracts, Hash - Hard



Terpenes

Analyte	LOQ	Mass	Mass	Analyte	LOQ	Mass	Mass
	%	%	mg/g		%	%	mg/g
β-Caryophyllene	0.001	0.168	1.68	Borneol	0.001	0.003	0.03
trans-Nerolidol	0.001	0.132	1.32	Camphene	0.001	0.003	0.03
α-Bisabolol	0.001	0.104	1.04	Fenchone	0.001	0.003	0.03
Farnesene	0.001	0.059	0.59	Sabinene Hydrate	0.001	0.003	0.03
α-Pinene	0.001	0.054	0.54	Terpinolene	0.001	0.003	0.03
Limonene	0.001	0.047	0.47	3-Carene	0.001	ND	ND
α-Humulene	0.001	0.044	0.44	α-Cedrene	0.001	ND	ND
β-Pinene	0.001	0.030	0.30	α-Phellandrene	0.001	ND	ND
Linalool	0.001	0.026	0.26	α-Terpinene	0.001	ND	ND
Phytol	0.001	0.025	0.25	Camphor	0.001	ND	ND
α-Terpineol	0.001	0.019	0.19	γ-Terpinene	0.001	ND	ND
Guaiol	0.001	0.017	0.17	Geraniol	0.001	ND	ND
cis-Nerolidol	0.001	0.013	0.13	Geranyl Acetate	0.001	ND	ND
Endo-Fenchyl Alcohol	0.001	0.012	0.12	Isoborneol	0.001	ND	ND
Caryophyllene Oxide	0.001	0.010	0.10	Isopulegol	0.001	ND	ND
β-Myrcene	0.001	0.009	0.09	Linalyl Acetate	0.001	ND	ND
Ocimene	0.001	0.005	0.05	Menthol	0.001	ND	ND
Cedrol	0.001	0.004	0.04	Nerol	0.001	ND	ND
Eucalyptol	0.001	0.004	0.04	Pulegone	0.001	ND	ND
Valencene	0.001	0.004	0.04	Sabinene	0.001	ND	ND
				Total		0.801	8.01

Primary Aromas











Method: GC-FID. LOQ = Limit of Quantitation; The reported result is based on a sample weight with the applicable moisture content for that sample; Unless otherwise stated all quality control samples performed within specifications established by the Laboratory. ND = Not Detectable, NR = Not Reported, NT = Not Tested



1140 Fisher Road Cobble Hill, BC (250) 929-2002 https://www.puralabs.ca Lic# LIC-RJMAT2OG6I-2019

Ach

Denise Johnson Head of Laboratory

Confident Cannabis All Rights Reserved support@confidentcannabis.com (866) 506-5866 www.confidentcannabis.com





Certificate of Analysis

Powered by Confident Cannabis 3 of 3

Cannabis Care

XXXX Vancouver Island, BC XXX XXX help@cannabiscare.cc (888) 798-6710 Lic.# Sample: 2108PURA0440.1409

Strain: Medi Hash Batch#: ; Batch Size: 1 g

Sample Received: 08/16/2021; Report Created: 08/18/2021

Medi Hash

Concentrates & Extracts, Hash - Hard



Residual Solvents Pass

Analyte	LOO	Limit	Mass	Status
	PPM	PPM	PPM	<u> </u>
1-Butanol	50.000	5000.000	ND	Pass
1-Pentanol	50.000	5000.000	ND	Pass
2-Butanol	50.000	5000.000	ND	Pass
2-Butanone	50.000	5000.000	ND	Pass
2-Methyl-1-Propanol	50.000	5000.000	ND	Pass
3-Methyl-1-Butanol	50.000	5000.000	ND	Pass
Acetic acid	500.000	5000.000	ND	Pass
Acetone	50.000	5000.000	ND	Pass
Anisole	50.000	5000.000	ND	Pass
Butanes	50.000	5000.000	ND	Pass
Butyl Acetate	50.000	5000.000	ND	Pass
Dimethyl Sulfoxide	50.000	5000.000	ND	Pass
Ethanol	50.000	5000.000	ND	Pass
Ethyl-Acetate	50.000	5000.000	ND	Pass
Ethyl-Ether	50.000	5000.000	ND	Pass
Ethyl-Formate	50.000	5000.000	ND	Pass
Formic Acid	500.000	5000.000	ND	Pass
Heptane	50.000	5000.000	ND	Pass
sobutyl-Acetate	50.000	5000.000	ND	Pass
sopropanol	50.000	5000.000	186.800	Pass
sopropyl-Acetate	50.000	5000.000	ND	Pass
Methyl-Acetate	50.000	5000.000	ND	Pass
n-Propanol	50.000	5000.000	ND	Pass
n-Propyl-Acetate	50.000	5000.000	ND	Pass
Pentanes	50.000	5000.000	ND	Pass
Propane	50.000	5000.000	ND	Pass
Fert-Butyl-Methyl-Ether	50.000	5000.000	ND	Pass
Triethylamine	50.000	5000.000	ND	Pass

 $\overline{\text{LOQ}}$ = Limit of Quantitation; The reported result is based on a sample weight with the applicable moisture content for that sample; Unless otherwise stated all quality control samples performed within specifications established by the Laboratory.ND = Not Detectable, NR = Not Reported, NT = Not Tested



1140 Fisher Road Cobble Hill, BC (250) 929-2002 https://www.puralabs.ca Lic# LIC-RJMAT2OG6I-2019

Denise Johnson Head of Laboratory Confident Cannabis All Rights Reserved support@confidentcannabis.com (866) 506-5866 www.confidentcannabis.com

